

STS Dash

STS Dash: STS Signal Dashboard.

- Display 1 to 4 time-frames of the current STS signals.
- 2 Optional alerts that can be set to alert when specified time-frames line up.
- User configurable colors.
- 5 different arrow types.
- Position relative to the on top-left or top right corner.

NOTE!

STS-Dash REQUIRES MT4 Build 419.

If it crashes your copy of MT4, remove it from the indicators folder and restart MT4.

Direct your complaints about crashes to Metaquotes who are responsible for backward compatibility and the stability of their product.



Indicator Parameters

TimeFrame.Settings

TimeFrame.1=M1 Timeframe.
TimeFrame.2=M5 M1,M5,M15,M30;H1,H4,D1,W1,MN1.
TimeFrame.3=M15 1,5,15,30,60,240,1440,10080,43200.
TimeFrame.4=H1 Do not display: 0 or NULL String.

TimeFrame.TF1BarNr=0 Bar nr to display data for. 'Currently open bar'=0, 'Last closed bar'=1.
TimeFrame.TF2BarNr=0
TimeFrame.TF3BarNr=0
TimeFrame.TF4BarNr=0

TVI.Settings

TVI.r=12 TVI r Period.
TVI.s=12 TVI s Period.
TVI.u=5 TVI u Period.
TVI.Label="TVI" Label for the TVI signal line.

CCI.Settings

CCI.Period=20 CCI Period.
CCI.Label=CCI Label for the CCI signal line.

GoldMiner.Settings

GoldMiner.SSP=7 SSP Period.
GoldMiner.KMax=50.6 Kmax Value.
GoldMiner.Label=GM Label for the GoldMiner signal line.

BullsBears.Settings

BullsBears.Period=12 BullsBears Period.
BullsBears.Classic=True Classic mode true: Iterate up from 0. Repaints more.
Classic mode false: Iterate down. Repaints less.
BullsBears.Label=BB Label for the BullsBears signal line.

Alert.Settings

Alert.Set1=1100 Alert flags for TF1, TF2, TF3, TF4.
Enable=1, Disable=0. Ex: 0101=TF2 AND TF4.
Alert.Set2=1010 Alert flags for TF1, TF2, TF3, TF4.
Enable=1, Disable=0. Ex: 1010=TF1 AND TF3.
Alert.OnBarClose=True Alert only when an open bar closes.
Alert.Popup=True Popup window & sound on alert.
Alert.Email=False Send email on alert.
Alert.Subject= Email Subject. Blank will result in a preconfigured subject.

Display.Settings

Display.X=5 X position of display.
Display.Y=15 Y position of display.
Display.Corner=0 Display corner. Top left=0, Top Right=1.
Display.SysFontSize=1.0 Display system font size zoom factor. Normal=1.0, 125% zoom=1.25.
Display.ColorBkg1=Gray Background color for odd line.
Display.ColorBkg2=Gray Background color for even line.
Display.ColorHeader=Gold Color of the header text.
Display.ColorSignal=Blue Color of the symbol text.

Display.ColorUp=Green	Color of the up signal.
Display.ColorDown=Red	Color of the down signal.
Display.ArrowType=0	0=Arrow, 1=Diagonal Arrow, 2=Square, 3=Dot, 4=Diamond.