

## Currency Strength Meter Installation

The screenshot shows a Microsoft Excel spreadsheet titled "Jim-SuperMeter.xls". The spreadsheet contains the following data:

Weights		0.963928	0.999840616	0.980315618		0.98291689						
		Euro/Dollar	Pound/Dollar	Dollar/swiss		Loonie/Dollar						
		EUR/USD	GBP/USD	AUD/USD	USD/JPY	USD/CHF	USD/CAD	EUR/AUD	EUR/CAD	EUR/CHF	EUR/GBP	EUR/JPY
High		1.4816	1.9598	0.8965	108.9600	1.1012	1.0204	1.6621	1.5103	1.6300	0.7563	161.2800
Ask		1.4810	1.9587	0.8956	108.8000	1.1008	1.0197	1.6549	1.5104	1.6301	0.7564	161.1100
Bid		1.4808	1.9583	0.8952	108.7700	1.1005	1.0192	1.6532	1.5093	1.6297	0.7561	161.0700
Low		1.4782	1.9575	0.8890	108.6000	1.0984	1.0175	1.6511	1.5060	1.6267	0.7549	160.5400
PIP Range		34	23	75	36	28	29	110	43	33	14	74
Bid Ratio		76.5%	34.8%	82.7%	47.2%	75.0%	58.6%	19.1%	76.7%	90.9%	85.7%	71.6%
Relative Strength	EUR	GBP	AUD	USD	USD	USD	EUR	EUR	EUR	EUR	EUR	EUR
	7	3	7	4	7	5	2	7	8	7	6	
	USD	USD	USD	JPY	CHF	CAD	AUD	CAD	CHF	GBP	JPY	
	2	6	2	5	2	4	7	2	1	2	3	
Total Strength	USD	EUR	GBP	CHF	CAD	AUD	JPY	NZD	Strong			
	4.1	6.2	3.8	2.3	2.67	7.0	4.0	6.0	Rising			
# of evaluation points	7	6	4	3	3	4	5	1	Neutral			
	-1				3				Weak			
Relative Strength1	GBP	GBP	NZD	AUD	AUD	CHF	AUD	NZD	#/ALUE!			
	4	6	6	7	7	4	0	4	#/ALUE!			
	JPY	CHF	USD	CAD	JPY	JPY	9	9	#/ALUE!			
	5	3	3	2	2	5			#/ALUE!			
PIP Range1	84	50	67	71	102	42	105	#/ALUE!				
Bid Ratio1	47.6%	64.0%	61.2%	81.7%	76.5%	45.2%	0.0%	#/ALUE!				


### Requirements:

- Microsoft Excel Software.
- MetaTrader 4.0 Platform. The currency meter seems to work best with MT4 from FXDD. You may open a free demo account and download MT4 platform from this link: <http://www.fxdd.com/en/forex-trading-software/metatrader.html>

1. Download and Install MT 4 Platform – if you don't already have it.

## 2. Enable DDE Server in the MT4 Platform


Once MT4 platform is installed, open platform, click on the "Tools" tab and then click on "Options". The Options window will come up; check the box next to "Enable DDE server" as shown below and click on the "OK" button to save your settings.




## 3. Open Strength Meter

Once you have enabled the DDE server option in MT4, you may open the Strength meter spreadsheet. You will need to have MT4 open every time before opening the meter.


Upon opening the spreadsheet, you may be asked to enable macros. Click on Enable Macros.



Then click on "Update" to retrieve data from MT4.



You may also be asked about links that cannot be updated, just click on "Continue".



Once the spreadsheet opens up, you should see something similar as the 1<sup>st</sup> picture on top.